

NO. 20 NEW YORK



VERSION 3



















Sewing

NB! THE PATTERN HAS 1 CM SEAM ALLOWANCES INCLUDED UNLESS OTHERWISE NOTED.


1. Cut out all pieces in fabric

NB!

- a. Pattern piece A, C & H is cut on bias.
- 2. Overlock:
- Side seam top-front piece
- Side seam top-back piece
- Side seam bottom-front
- Side seam bottom-back




- 3. Sew the top side seams, right sides together.
- 4. Sew the bottom side seams, right sides together.






- 5. Press all seams open.
- 6. Sew the bias band to the top-back piece from the back to the notch at the front. See a guide online.



- Place the right side of the bias band to the wrong side of the top.
- Sew with a seam allowance of 0.7 cm press the bias band out.
- Fold the raw edge of the bias band to the raw edge of the top.
- Fold the bias band around the edge of the top.
- Topstitch the bias binding in place, 0.2 cm from the edge.



Finish the edge and make the strap

- 7. Sew the bias tape to the top-front over the bias band you just sew. Let a tail of approx. 45 cm hang from the end, this is going to be your strap. When sewing the top stitch of the bias band continue the top stitch and finish at the end end of the tail.
- 8. Machine baste a gathering thread between the notches on the top-front piece.







- 10. Pin the top to the bottom and gather between the notches. The top-front and the top-back pieces are overlapping.
- 11. Sew the top and bottom together.
- 12. Overlock the seam and press down.



- 13. Finish the chemise with a narrow hem.
- 14. Adjust the straps, so they fit you and sew them onto the back.

